


McCALL'S®

FIVE-POCKET SHOWER ORGANIZER

FREE PROJECT




1. Baste INTERFACING to wrong side of each matching FABRIC section, having raw edges even.




2. Press under 1/4" (6mm) on upper edge UPPER POCKET. Turn upper edge to inside on hemline. Stitch hem in place along pressed under edge.




3. To make center pleat, crease on line with small circles and bring to line of large circles. Press. Baste across upper and lower edges of pleats. Make side pleats in same manner.



4. Press under 1/2" (1.3cm) on lower edge of pocket.



5. With right sides up, pin pocket to one FRONT AND BACK section, placing lower edge along placement line and matching large circles. EDGESTITCH lower edge in place. Baste side edges.



SUGGESTED FABRICS:

Fabric: Nylon; Pockets: Mesh

YOU WILL NEED:

Fabric: 45" - 60" wide - 1/2 yd.

Mesh (pockets): 60" wide - 1/2 yd.

Sew-in Interfacing: 21" - 25" wide - 1 yd.


Notions: Two 7/8" buttons **OR** Qwik-Tack™ Tape and Flex-On™ Loops

Please read all the instructions before you start your project.


All seam allowances are 1/2" (13mm) unless otherwise indicated.

SHOWER ORGANIZER pg. 2


6. Remove pleat basting. Stitch pocket along stitching line, keeping pleats free. Baste side edges together.




11. Pin front and back sections, right sides together. Stitch, leaving an opening for turning.




16. Turn right side out. Press. Baste raw edges together. Stitch along previous stitching on pockets through all thicknesses. EDGESTITCH outer edges of caddy.




7. Finish upper edge of LOWER POCKET 3 in same manner as upper pocket. Pin pocket to lower edge of front and back, matching large circles and having raw edges even. To form sections, stitch pocket along stitching lines. Baste raw edges together. NOTE: Caddy can be finished with straps or optional tape and loops.



12. Turn right side out. SLIPSTITCH opening edges. Press.




17. Beginning and ending between loops without slit, cut a piece of Qwik-Tack® Tape 10" (25.5cm) long.




8. For each strap, stitch two STRAP sections leaving ends with circles free.



13. Stitch along previous stitching on pockets through all thicknesses. EDGESTITCH outer edges of caddy. TOPSTITCH 1" (2.5cm) from upper edge of caddy.




18. Slip caddy between folds of tape, having outer edges even. EDGE-STITCH and TOPSTITCH lower edge of tape.




9. Turn right side out. Press. Baste raw edges together.




14. Make buttonholes on ends of straps. Cut buttonholes open. Sew buttons to caddy at markings.



20. Place Flex-On® Loops with prongs on right side of Qwik-Tack® Tape, aligning slit in ring with opening in fabric and inserting prongs into holes. Snap remaining LOOPS® section over prongs, matching slit opening. To hang caddy, slide LOOPS® over rod.




10. Pin straps to upper edge of front and back, matching small circles. Baste.







OPTIONAL TAPE AND LOOPS:

15. Pin front and back sections, right sides together. Stitch sides and lower edge.



ENLARGE ALL PATTERN PIECES 200%





**ENLARGE
ALL
PATTERN
PIECES
200%**